
# **WAXIE Bombers Industrial Strength Stripper**



Item: 320824 gl 4/cs Item: 320822 5 gl drum Secondary Label: 320824LBL

## **APPLICATION**











### **FEATURES & BENEFITS**

- Professional-strength
- Non-ammoniated
- Mild odor
- Fast-acting
- High productivity

### **DESCRIPTION**

Ultra-strength stripper formulated for removing extra-heavy buildup of waxes, floor finishes and sealers. Non-ammoniated, mild odor. Can be used on all modern resilient and hard surface floors.

# **SPECIFICATIONS**

	AS SOLD	USE DILUTION
Appearance	Amber liquid	Colorless to yellow
Odor	Solvent	Slight solvent
pH	12.0-14.0	10.0-12.0
VOC	N/A	N/A
Melting Point/Freezing Point	Not determined	Approx. 0°C (32°F)
Initial Boiling Point/Boiling Range.	> 99°C (210°F)	Approx. 100°C (212°F)
Flash Point	N/A	N/A
Flammability	N/A	N/A
Relative Density (Density)	1.04 (8.67 lb/gal)	Approx. 1.0 (8.34 lb/gal)
Solubility	Completely soluble in water	.Completely soluble in water

#### **ACTIVE INGREDIENTS:**

Potassium Hydroxide Solution	Proprietary <sup>1</sup>
1-Amino-2-Propanol	Proprietary
2-Butoxyethanol	Balance

<sup>&</sup>lt;sup>1</sup> The exact percentage of composition has been withheld as a trade secret. All relevant physical and health hazards have been declared, in accordance with regulatory requirements.

**SHELF LIFE:** All WAXIE brand chemical products have a guaranteed shelf life of up to one year after the date product was manufactured, when stored in ambient conditions. The actual manufacturing date is included in a date code on every product container.

## **DIRECTIONS FOR USE**

Wear safety goggles and Latex, Nitrile or Neoprene gloves for you protection when handling this product.

Using a mop, sprayer or sprinkler can, liberally apply solution to the floor and let it work for 5 to 15 minutes (do not allow to dry). Machine scrub with a synthetic stripping or buildup removal pad. Pick up old finish and soil with a wet/dry vacuum or with a mop and bucket. Rinse thoroughly. For best results, a neutralizer should be used in the final rinse. Let floor dry completely before recoating.

For detail work and baseboards, use a trigger sprayer to liberally apply solution onto baseboards and edges and into corners. Let solution work for 5 to 10 minutes (do not allow to dry). Agitate with corner brush or a heavy-duty synthetic pad. (Use caution to avoid scratching baseboards with a synthetic pad). Rinse and let it dry. (We do not recommend applying finish to baseboards unless they are very worn and faded.)

Page 1 of 2



# **WAXIE Bombers Industrial Strength Stripper**

# **DIRECTIONS FOR USE (CONTINUED)**

**NOTE:** WAXIE Bombers is formulated for extreme buildups and should not be used for normal maintenance. When using WAXIE Bombers, never let it dry; always keep it fluid. On old floor surfaces, test a small, inconspicuous area first a dilution of 32 ounces of WAXIE Bombers to 1 gallon of water (1:4) to determine resiliency and compatibility. If there are any adverse effects, discontinue the use of this product immediately. **Extremely Heavy Buildup:** Dilute 21 ounces of WAXIE Bombers to 1 gallon of water (1:6). **Heavy to Medium Buildup:** Dilute 8 ounces of WAXIE Bombers to 1 gallon of water (1:16).

NOTE: Do not allow concentrate to touch floors. Not for use on asphalt or linoleum floors.

## **SAFETY INFORMATION**



Read the Safety Data Sheet (SDS) and product label before use. The SDS and product label contain hazard warnings, precautionary statements and first aid procedures. SDS documents are available online at www.waxie.com or by calling (800) 995-4466.

For sale to, use and storage by service professionals only. Keep out of reach of children.

HOTLINE NUMBER: You may contact Chem-Tel at (800) 255-3924 for emergency medical treatment information.

